

Tableau Server on Windows in the Google Cloud Platform

Administrator Guide

Last Updated 22/02/2024

© 2024 Salesforce, Inc.



Contents

Install Tableau Server on the Google Cloud Platform	1
This is archived content	1
Introduction	1
Tableau Server on the Google Cloud Platform deployment options	2
This is archived content	2
Introduction	3
What You Need Before You Begin	4
This is archived content	4
Introduction	4
Best Practices for Installing Tableau Server on the Google Cloud Platform	5
This is archived content	5
Introduction	5
Keeping Costs Down	6
Tableau Server on the Google Cloud Platform Topology	6
This is archived content	6
Introduction	7
Selecting a Google Compute Engine Virtual Machine Type and Size	8
This is archived content	8
Introduction	9
Typical VM types and sizes for development, test and production environments	9
Recommended specifications for a single production instance	9

Self-Deploy a Single Tableau Server on the Google Cloud Platform	11
This is archived content	11
Introduction	11
Step 1: Set up a Google Compute Engine VM	12
Step 2: Connect to your Google Compute Engine VM	13
Step 3: Install Tableau Server on your Google Compute Engine VM	14
Step 4: Access Tableau Server from a remote browser	15
Step 5: Publish data to Tableau Server on your Google Compute Engine VM	16
Step 6: Manage Tableau Server licences	16
Self-Deploy Tableau Server on the Google Cloud Platform in a Distributed Environment	17
This is archived content	17
Introduction	18
Step 1: Create a Google Cloud Platform Virtual Private Cloud (VPC)	18
Step 1: Create a Google Cloud Platform HIPAA-aligned project	19
Step 2: Deploy Three Google Compute Engine VMs	19
Step 3: Create a Google Cloud Platform Load Balancer for the Tableau Server Cluster	20
Troubleshooting Tableau Server on the Google Cloud Platform	21
This is archived content	21
Introduction	22

Install Tableau Server on the Google Cloud Platform

This is archived content

Deployments on public clouds continue to be supported but the content for third-party public cloud deployments is no longer updated.

For the latest Tableau Server deployment content, see the [Enterprise Deployment Guide](#) and the [Deploy](#) section of Tableau Server help.

For those customers who have access, we recommend Tableau Cloud. For more details, see:

- [Tableau Cloud Manual Migration Guide](#)
- [Tableau Cloud Trial for Admin](#)
- [Tableau Cloud: Get Started for Admin](#)

Introduction

When you install Tableau on a Google Compute Engine (GCE) virtual machine (VM), you still have the advanced capabilities of Tableau in a local environment. Running Tableau on a GCE VM is an excellent choice if you want the flexibility of scaling up and scaling out without having to purchase and maintain an expensive fleet of servers. For instance, you can configure Tableau to be highly available, and integrate with all the common enterprise applications (for example, Active Directory) that many organisations rely on.

Looking for Tableau on Linux? See [Install Tableau Server on the Google Cloud Platform](#).

Tableau can take advantage of many native Google Cloud Services:

- [Google Persistent Disk](#): Cloud-based block storage for virtual machines (VMs).
- [Google Cloud Storage](#): Cloud-based unified object storage for data archiving.
- [Google Cloud Dataflow](#): Cloud-based service for stream and batch data processing.
- [Google Cloud Dataproc](#): Cloud-based service for running Spark and Hadoop clusters.

In addition, you can store the data you use with Tableau Server using any of the following Google Cloud Services. Tableau provides native data [connectors](#) that enable you to connect to data in the following Google data sources:

- [Google Analytics](#): Web analytics tool for tracking and reporting website traffic.
- [Google BigQuery](#): Managed enterprise data warehouse for analytics.
- [Google Cloud SQL](#): Managed SQL database service.
- [Google Sheets](#): Spreadsheet included in Google Docs.

Tableau Server on the Google Cloud Platform deployment options

This is archived content

Deployments on public clouds continue to be supported but the content for third-party public cloud deployments is no longer updated.

For the latest Tableau Server deployment content, see the [Enterprise Deployment Guide](#) and the [Deploy](#) section of Tableau Server help.

For those customers who have access, we recommend Tableau Cloud. For more details, see:

- [Tableau Cloud Manual Migration Guide](#)
- [Tableau Cloud Trial for Admin](#)
- [Tableau Cloud: Get Started for Admin](#)

Introduction

You can deploy Tableau Server on a Google Compute Engine (GCE) virtual machine (VM). A Tableau deployment on GCE supports the following:

Tableau Server	Google Compute Engine VM Self-Deployment
Production ready	
Upgrade Tableau without replacing the VM	
Install on Linux	
Install on Windows	
Scale-up	
Scale-out (add nodes)	
Active Directory support	
BYOL licence	

The self-deployment option is described in more detail below:

- **Self-Deploy to Google Compute Engine VM** – Provides the most flexibility and options to customise Tableau Server to your environment.

Self-deployment of Tableau Server on a Google Compute Engine VM is recommended for development, test, and production environments that start simple but may need to scale later.

For more information about self-deployment, see [Self-Deploy a Single Tableau Server on the Google Cloud Platform](#). For more information about deploying in a distributed

Tableau Server on Windows in the Google Cloud Platform Administrator Guide environment, see [Self-Deploy Tableau Server on the Google Cloud Platform in a Distributed Environment](#).

For more information about Tableau licensing options, search for "Licensing Overview" in the Tableau Help.

What You Need Before You Begin

This is archived content

Deployments on public clouds continue to be supported but the content for third-party public cloud deployments is no longer updated.

For the latest Tableau Server deployment content, see the [Enterprise Deployment Guide](#) and the [Deploy](#) section of Tableau Server help.

For those customers who have access, we recommend Tableau Cloud. For more details, see:

- [Tableau Cloud Manual Migration Guide](#)
- [Tableau Cloud Trial for Admin](#)
- [Tableau Cloud: Get Started for Admin](#)

Introduction

To work with Tableau Server on the Google Cloud Platform, you will need:

- A Google Cloud Platform account. If you don't already have one, [sign up for a new account](#).
- A Tableau licence.
 - For a standalone Tableau Server deployment, you must [contact sales](#) for a product key.

- For a cluster-based deployment, you need a user-based licence (which covers all authorised users of Tableau), a core-based licence (with a minimum of 16 cores) or a Tableau subscription licence. To obtain a product key, [contact sales](#).

For more information about Tableau licensing options, search for "Licensing Overview" in the Tableau Help.

Best Practices for Installing Tableau Server on the Google Cloud Platform

This is archived content

Deployments on public clouds continue to be supported but the content for third-party public cloud deployments is no longer updated.

For the latest Tableau Server deployment content, see the [Enterprise Deployment Guide](#) and the [Deploy](#) section of Tableau Server help.

For those customers who have access, we recommend Tableau Cloud. For more details, see:

- [Tableau Cloud Manual Migration Guide](#)
- [Tableau Cloud Trial for Admin](#)
- [Tableau Cloud: Get Started for Admin](#)

Introduction

The following best practices make installing Tableau Server in the cloud a better experience.

- Search for "Plan Your Deployment" in the Tableau Server Help.
- Read the Tableau Server on [Google Cloud Platform Prerequisites](#).
- Search for "Security Hardening Checklist" in the Tableau Server Help

- If you're new to the cloud, use the [Google Cloud Platform free tier](#) to get familiar with working in the cloud before you deploy Tableau Server on the Google Cloud Platform.
- Read Google Cloud Platform [best practices for enterprise organisations](#).
- Read about and understand [network topology](#) on the Google Cloud Platform and how to architect it.

Keeping Costs Down

The Google Cloud Platform offers cloud-based services on a pay-as-you-go basis. Costs are determined by the services you run and amount of time you use them. Different combinations of instance types and sizes have different costs. For more information about services pricing, see [Google Cloud Platform pricing](#). You can estimate your total monthly costs using the [Google Cloud Platform pricing calculator](#). You can also compare on-premises vs the cloud using the [Google Cloud Platform TCO calculator](#).

To help monitor and control usage costs on an ongoing basis, you can set up billing alerts for the Google Cloud Platform to alert you when your monthly Google Cloud Platform costs reach your predefined spending threshold. For more information, see [Set budgets and alerts](#) at the Google website.

Tableau Server on the Google Cloud Platform Topology

This is archived content

Deployments on public clouds continue to be supported but the content for third-party public cloud deployments is no longer updated.


For the latest Tableau Server deployment content, see the [Enterprise Deployment Guide](#) and the [Deploy](#) section of Tableau Server help.

For those customers who have access, we recommend Tableau Cloud. For more details, see:

- [Tableau Cloud Manual Migration Guide](#)
- [Tableau Cloud Trial for Admin](#)
- [Tableau Cloud: Get Started for Admin](#)


Introduction

When deploying Tableau Server on the Google Cloud Platform, you may choose the level and depth of integration between Tableau Desktop and Tableau Server on your Google Compute Engine (GCE) virtual machines (VMs). You can use Tableau Desktop and its ability to extract data from your data sources to act as a bridge between your data and Tableau. Based on your needs, or if you already have a lot of data in the Google Cloud Platform, you might instead choose to leverage the full range of Google Cloud Platform services in conjunction with Tableau Server. The following diagram shows data source integration with Tableau Desktop and Tableau.



In the following diagram, all of your data is hosted on the Google Cloud Platform. You can analyse both structured and unstructured data managed in a secure, scalable manner. You may leverage data that resides on the Google Cloud Platform only, unmanaged data that lives outside of the Google Cloud Platform or a combination of both. This flexibility greatly increases

the ability of your organisation to support moves to the cloud from on-premise data, since both types of data are supported equally.



Selecting a Google Compute Engine Virtual Machine Type and Size

This is archived content

Deployments on public clouds continue to be supported but the content for third-party public cloud deployments is no longer updated.

For the latest Tableau Server deployment content, see the [Enterprise Deployment Guide](#) and the [Deploy](#) section of Tableau Server help.

For those customers who have access, we recommend Tableau Cloud. For more details, see:

- [Tableau Cloud Manual Migration Guide](#)
- [Tableau Cloud Trial for Admin](#)
- [Tableau Cloud: Get Started for Admin](#)

Introduction

The Google Cloud Platform offers many types of Google Compute Engine (GCE) virtual machines (VMs) in various sizes. Choosing the right VM for your workload is an important factor for a successful Tableau Server deployment. You can choose from a wide range of VMs. For a complete list of all available VM types and sizes, see the [Machine Types](#) page at the Google website.

It is important to select a VM that can run Tableau Server. The VM must meet the Tableau Server hardware guidelines (a minimum of 8 cores and 128 GB of RAM).

At minimum, a 64-bit Tableau Server requires a 4-core CPU (the equivalent of 8 Google Compute Engine vCPUs) and 64 GB RAM. However, a total of 8 CPU cores (16 Google Compute Engine vCPUs) and 128 GB RAM are strongly recommended for a single production Google Compute Engine VM.

The Windows Operating system will recognise these 16 vCPU as 8 cores, so there is no negative licensing impact.

Typical VM types and sizes for development, test and production environments

- n2-standard-16

Recommended specifications for a single production instance

Component/Resource	Google Cloud Platform				
CPU	16+ vCPU				
Operating System		2019.x	2020.1.0 - 2021.2.x	2021.3.0	2023.3.1+
	Windows				

Tableau Server on Windows in the Google Cloud Platform Administrator Guide

	2019.x	2020.1.0 - 2021.2.x	2021.3.0	2023.3.1+
Server 2008 R2				
Windows Server 2012	✓	✓		
Windows Server 2012 R2	✓	✓		
Windows Server 2016	✓	✓	✓	✓
Windows Server 2019	✓	✓	✓	✓
Windows Server 2022	<p>Note: Windows Server 2022 is <i>not</i> supported in versions prior to 2023.3.1. Beginning in April 2023, installers for all versions of Tableau Server on Windows prior to 2023.3.1 block installation on Windows 2022.</p>			✓
Memory	128+ GB RAM (4 GB RAM per vCPU)			
Storage	Two volumes: 30-50 GiB volume for the operating system			

	100 GiB or larger volume for Tableau Server
Storage type	SSD persistent disk, 200GB++ For more information about SSD persistent disks, see Storage Options at the Google Cloud Platform website.
Disk latency	Less than or equal to 20ms as measured by the Avg. Transfer disk/sec Performance Counter in Windows.

Self-Deploy a Single Tableau Server on the Google Cloud Platform

This is archived content

Deployments on public clouds continue to be supported but the content for third-party public cloud deployments is no longer updated.

For the latest Tableau Server deployment content, see the [Enterprise Deployment Guide](#) and the [Deploy](#) section of Tableau Server help.

For those customers who have access, we recommend Tableau Cloud. For more details, see:

- [Tableau Cloud Manual Migration Guide](#)
- [Tableau Cloud Trial for Admin](#)
- [Tableau Cloud: Get Started for Admin](#)

Introduction

You can install and run Tableau Server on a Google Compute Engine (GCE) virtual machine (VM). Perform the following tasks to install and configure Tableau Server on a Google Compute Engine VM.

Step 1: Set up a Google Compute Engine VM

Create a Google Compute Engine virtual machine (VM) where you'll install Tableau.

1. Sign in to the [Google Cloud Platform Console](https://console.cloud.google.com/) (https://console.cloud.google.com/).
2. If you haven't already, create a new project and set up billing. For more information, see [Creating and Managing Projects](#) at the Google website.
3. On the Google Cloud Platform dashboard, in the navigation pane, under **Compute**, click **Compute Engine**.
4. In the **Compute Engine VM instances** dialog box, click **Create**.
5. On the **Create an instance** page, specify the following instance properties:
 - a. **Name:** Enter a name for your virtual machine (VM).
 - b. **Zone:** To help reduce latency, choose the zone closest to your data source and users.
 - c. **Machine type:** Select a VM that meets the [system requirements](#) for Tableau Server. For example, select the **n1-standard-16** machine type, click **Customise** and then increase the memory to **64 GB**.
 - d. **Container:** If selected, untick the **Deploy a container image to this VM instance** box (the default).
 - e. **Boot disk:** Click **Change**, and then select **Windows Server 2016 Datacenter** with a 128 GB SSD persistent disk, and then click **Select**.
 - f. **Identity and API access:** Use the default setting.
 - g. **Firewall:** Select **Allow HTTP traffic** and **Allow HTTPS traffic**.
6. When you've finished the settings, review your selections and then click **Create**.

Step 2: Connect to your Google Compute Engine VM

After you create your Google Compute Engine (GCE) virtual machine (VM), you must connect to it and prepare it to install Tableau.

1. In the **Compute Engine** console, click **VM instances**.
2. In the list of VM instances, select your instance.
3. In the **Connect** column, click the **RDP** pop-up menu, click **Set Windows password**.
4. On the **Set new Windows password** dialog box, in the **Username** field, specify a username (or leave the default one). Store the username in a safe place.
5. Click **Set** to generate a password. It might take several seconds before the **New Windows password** dialog box appears. Store the password in a safe place.

Important: This is your only chance to copy the password.

6. On the **VM instances** page, in the **Connect** column, click the **RDP** pop-up menu, and then select **Download the RDP file**. Save the .rdp file to your computer.
7. Connect to your VM using the .rdp file you saved. Provide the username and password you generated above for the Google Compute Engine VM. (If you're already signed into a Windows network, such as your organization's network, choose **Other User** and enter your credentials in those boxes.)

You will see one or more messages telling you that the remote connection cannot be identified. This is normal.

Note: The RDP file references the instance by using an external IP address. By default, this is an ephemeral IP address, which might be renewed when you stop or

restart the server. In that case, you'll need to get a new copy of the RDP file. For longer-term use, GCP provides static IP addresses at additional cost.

Remote Desktop signs you in to the Google Compute Engine VM.

For more information about how to connect to Google Compute Engine VMs, see [Connecting to Instances](#) at the Google website.

Step 3: Install Tableau Server on your Google Compute Engine VM

Installing Tableau on a Google Compute Engine (GCE) virtual machine (VM) is similar to installing it on any other server.

Notes:

- You can select local authentication or Active Directory (AD) authentication only during initial installation. AD is only required for multi-worker configurations. For more information, see [Setting up Active Directory on Google Compute Engine](#) at the Google website.
- The Run As user must be a local user on the server instance.

1. Copy the Tableau Server installation program to your VM by doing one of the following:
 - **Download the installer directly.** While logged into the VM, open a browser, browse to the [Tableau Server download page](#), and download the version of Tableau appropriate for your operating system.

Note: The default enhanced security configuration on Windows Server dictates that Internet Explorer is always set to High for the Internet zone and

cannot be changed for that zone. Therefore, as you browse to public sites using Internet Explorer, you must add those sites to the list of trusted sites.

- **Copy the installer to the VM.** If you already have a copy of the Tableau installer on your computer, copy it to the VM. Create a folder on the VM where you want to put the installer. From your computer, upload the Tableau installer file (for example, tableau-server-2020-2-3.x86_64.rpm) to the VM. For more information about how to copy files to a Google Compute Engine VM, see [Transferring Files to Instances](#) at the Google website.
2. Run the Tableau installer on the VM to start the server installation process. The installation process works the same as it does on any other server. For more information, search for "Install and Configure Tableau Server" in the Tableau Help.

Step 4: Access Tableau Server from a remote browser

Make sure that only authorised users can access the Google Compute Platform virtual machine (VM) where you've installed Tableau.

1. In the Google Compute Platform console, under **Compute**, click **Compute Engine**, and then click **VM instances**. Find the external IP address associated with the VM.
2. On another computer (not on the VM), open a browser.
3. In the browser, type the external IP address of the Tableau you installed on the VM. For example, `http://13.64.47.61`.

Note: The external IP is an ephemeral address. It is released when you stop the instance and a new external IP is assigned on restart. If you stop your instance, you may need to retrieve the new external IP address to access the server using your

browser. GCP provides persistent static IP addresses. This time the URL resolves correctly and you reach the sign-in page for your instance of Tableau Server.

4. Sign in using the credentials for the administrator user that you created at the end of the installation process. When you've signed in, you see the Tableau Server Content page.

For more information on controlling access to your Tableau Server, see "Identity Store" in the Tableau Server Help.

Step 5: Publish data to Tableau Server on your Google Compute Engine VM

After you set up Tableau Server on a Google Compute Engine (GCE) virtual machine (VM), authorised users in your organisation can publish workbooks and data sources to the server. The process works the same way that it does if Tableau is installed on premises, except that users must sign in to the server that is running on the VM.

Before you allow users to publish, make sure that each user has been created with the Publisher site role in Tableau Server and that the users have Publisher permissions. For more information, search for "Add Users to the Server" in the Tableau Help.

To publish workbooks and data sources to Tableau, users must sign in to the server by using the cloud server IP address using credentials they've been assigned. For more information, see [How to Publish Workbooks to a Tableau Server](#).

Step 6: Manage Tableau Server licences

You don't need to manage your Tableau Server licence if you shut down your Google Compute Engine (GCE) virtual machine (VM) using the Google Cloud Platform console or from inside the VM itself. When you [stop a Google Compute Engine VM](#) with persistent SSD disk

using the GCP Compute Engine console, the VM **does not incur charges**, but resources attached to the VM will still incur charges.

Deleting a VM deallocates all of its resources, including external storage. You might delete your VM when you no longer need it. Always deactivate your Tableau licence before you shut down and delete your VM.

Before you delete your VM, do the following:

1. Sign in to your VM.
2. Create a backup of Tableau, and then copy the `.tsbak` file to another location, such as [Google Cloud Storage](#), that will be accessible after the VM is no longer available. For more information, search for "Perform a Full Backup and Restore of Tableau" in the Tableau Help.
3. Use the `tsm licences deactivate` command to deactivate your Tableau product key. You can now shut down and delete your VM.

Self-Deploy Tableau Server on the Google Cloud Platform in a Distributed Environment

This is archived content

Deployments on public clouds continue to be supported but the content for third-party public cloud deployments is no longer updated.

For the latest Tableau Server deployment content, see the [Enterprise Deployment Guide](#) and the [Deploy](#) section of Tableau Server help.

For those customers who have access, we recommend Tableau Cloud. For more details, see:

- [Tableau Cloud Manual Migration Guide](#)
- [Tableau Cloud Trial for Admin](#)
- [Tableau Cloud: Get Started for Admin](#)


Introduction

You can run Tableau Server on two virtual machines (VMs) in a distributed environment, also known as a cluster. However, if you want to run Tableau Server in a highly available (HA) distributed environment, you need to launch three or more Google Compute Engine (GCE) virtual machines (VMs) of the same type and capacity and configure them as additional nodes. This scenario assumes that you have three Google Compute Engine VMs with Tableau Server installed on each instance. One instance is configured as the initial node, and the other two instances are configured as additional nodes.

Use the following steps to install and deploy Tableau Server on a cluster of three Google Compute Engine VMs in a highly available and scalable configuration.


Step 1: Create a Google Cloud Platform Virtual Private Cloud (VPC)

You must have an existing Google Cloud Platform custom mode Virtual Private Cloud (VPC) with a private and a public subnet across three different zones. For information about how to plan and create a custom mode VPC network with custom subnets, see [Using VPC Networks](#) at the Google website.



Step 1: Create a Google Cloud Platform HIPAA-aligned project


Referring to the [Setting up a HIPAA-aligned Google Cloud project](#) tutorial, and relying on the Cloud Healthcare Data Protection Toolkit, this architecture helps you build a Google Cloud-based infrastructure with few steps by treating the configuration as code. The following diagram illustrates how the architecture helps you meet security and compliance best practices by using reusable building blocks: a Google Cloud Cloud Deployment Manager configuration script and parameterised configuration templates.



Step 2: Deploy Three Google Compute Engine VMs

Deploy three Google Compute Engine virtual machines (VMs) of the same type and capacity, in the private subnet, with each VM in its own zone. Select VMs that meet the [system requirements](#) for Tableau Server. You'll install Tableau Server on each of the Google Compute Engine VMs, and use one node as the initial server and the two other nodes as additional servers.

For more information about installing Tableau in a distributed Windows environment, search for "Distributed and Highly Available Installations" and "Install and Configure Additional Nodes" in the Tableau Server Help.



Step 3: Create a Google Cloud Platform Load Balancer for the Tableau Server Cluster

Read [Setting up a load balancer](#) at the Google website, and follow the steps to launch a load balancer within your Google Cloud Platform Virtual Private Cloud (VPC).

1. Create and launch either an Internet-facing load balancer or an internally accessible load balancer:
 - To launch a public, Internet-facing load balancer, follow the steps in [Setting Up HTTP\(S\) Load Balancing](#) at the Google website, and select the two public

subnets. Make sure that you configure the load balancer with SSL, as explained in [SSL Certificates](#) at the Google website.

- To launch an internally accessible load balancer, follow the steps in [Setting Up Internal Load Balancing](#) at the Google website, and select the two private subnets.
2. Ensure that your VPC network firewall rules are configured to allow access on port 80 or 443 only, with the source limited to hosts or ranges of hosts that will access Tableau. For more information about firewall rules, see [Firewall Rules Overview](#) at the Google website.
 3. Specify the ping path as /.
 4. Select the Tableau instances and follow the instructions in [Creating Cross-Region Load Balancing](#) at the Google website, so that the load balancer can balance the traffic across the instances in multiple zones.
 5. Update Tableau to use the load balancer. For more information, search for "Add a Load Balancer" in the Tableau Server Help.

Troubleshooting Tableau Server on the Google Cloud Platform

This is archived content

Deployments on public clouds continue to be supported but the content for third-party public cloud deployments is no longer updated.

For the latest Tableau Server deployment content, see the [Enterprise Deployment Guide](#) and the [Deploy](#) section of Tableau Server help.

For those customers who have access, we recommend Tableau Cloud. For more details, see:

- [Tableau Cloud Manual Migration Guide](#)
- [Tableau Cloud Trial for Admin](#)
- [Tableau Cloud: Get Started for Admin](#)

Introduction

If you're having trouble with Tableau on your Google Compute Engine (GCE) virtual machine (VM), or with getting access to Tableau after installation, review these troubleshooting tips.

- **Cannot connect to the VM using RDP**

One or more of the following issues might prevent you from connecting to your VM using RDP:

- Make sure you're using the right credentials.
- Choose the **Other User** option and enter your credentials there.
- Make sure that you're using a username that is valid on the GCP instance. For instance, if you created the instance with an administrator account of **myuser**, enter **.myuser** as the username in the RDP dialog box.

- **Cannot access the server from a remote browser**

One or more of the following issues might prevent you from accessing the server from a remote browser:

- Sign in to the instance and make sure that the server is running.
- In the instance, open a browser and access the server locally (for example, using `http://localhost` or `http://localhost:port`, where `port` is the port number that the server was configured to listen on).
- In the GCP Compute Engine console, make sure that you've configured an endpoint to allow HTTP traffic to the instance.

Note: You cannot use the Windows ping utility to test connectivity to the instance. The ping utility will always report a timeout when used from the public internet.

- **You receive the following error message: Tableau Server is unlicensed**

This error can occur if you've shut down instances without first deactivating the licence. Contact [Tableau Support](#).

- **Tableau Server does not use all CPU cores**

One or more of the following symptoms might occur when working with Tableau Server core-based licensing:

- When installing Tableau Server, the installer might show fewer cores than you would expect to see for the computer running Tableau Server.
- On the Licences page on Tableau Server, the number of cores listed under Licences in Use is less than you would expect to see.
- When you run `tsm licenses list`, Tableau Server might report fewer cores in use that you would expect to see.

For more information, see [Not All Cores Recognised by Tableau Server](#).